Balance Sheet Ratios

Ratio	How to Calculate	What it Means In Dollars and Cents		
Current	Current Assets Current Liabilities	Measures solvency: The number of dollars in Current Assets for every \$1 in Current Lialilites. For example: a Current Ratio of 1.76 means that for every \$1 of Current Liabilities, the company has \$1.76 in Current Assets with which to pay them.		
Quick	Cash + Accounts Receivable Current Liabilities	Measures liquidity: The number of dollars in Cash and Accounts Receivable for each \$1 in Current Liabilities. For example: a Quick Ratio of 1.14 means that for every \$1 of Current Liabilities, the company has \$1.14 in Cash and Accounts Receivable with which to pay them.		
Debt-to-Worth	Total Liabilities Net Worth	Measures financial risk: The number of dollars of Debt owed for every \$1 in Net Worth. For example: a Debt-to-Worth ratio of 1.05 means that for every \$1 of Net Worth that the owners have invested, the company owes \$1.05 of Debt to its creditors.		
	Income	Statement Ratios		
Gross Margin	Gross Profit Sales	Measures profitability at the Gross Profit level: The number of dollars of Gross Margin produced for every \$1 of Sales. For example: a Gross Margin Ratio of 34.4% means that for every \$1 of Sales, the company produces 34.4 cents of Gross Profit.		
Net Margin	Net Profit Before Tax Sales	Measures profitability at the Net Profit level: The number of dollars of Net Profit produced for every \$1 of Sales. For example: a Net Margin Ratio of 2.9% means that for every \$1 of Sales, the company produces 2.9 cents of Net Profit.		
Overall Efficiency Ratios				
Sales-To-Assets	Sales Total Assets	Measures the efficiency of Total Assets in generating sales: The number of dollars in Sales produced for every \$1 invested in Total Assets. For example: a Sales-To-Asset Ratio of 2.35 means that for every \$1 invested in Total Assets, the company generates \$2.35 in Sales.		
Return On Assets	Net Profit Before Tax Total Assets	Measures the efficiency of Total Assets in generating Net Profit: The number of dollars in Net Profit produced for every \$1 invested in Total Assets. For example: a Return on Assets Ratio of 7.1% means that for every \$1 invested in Assets, the company is generating 7.1 cents in Net Profit Before Tax.		

Return On	Net Profit Before Tax
Investment	Net Worth

Measures the efficiency of Net Worth in generating Net Profit: The number of dollars in Net Profit produced for every \$1 invested in Net Worth.

For example: a Return on Investment Ratio of 16.1% means that for every \$1 invested in Net Worth, the company is generating 16.1 cents in Net Profit Before Tax.

Specific Efficiency Ratios

Inventory Turnover	Cost of Goods Sold Inventory	Measures the rate at which Inventory is being used on an annual basis. For example: an Inventory Turnover Ratio of 9.81 means that the average dollar volume of Inventory is used up almost ten times during the fiscal year.
Inventory Turn-Days	360 Inventory Turnover	Converts the Inventory Turnover ratio into an average "days inventory on hand" figure. For example: a Inventory Turn-Days Ratio of 37 means that the company keeps an average of thirty-seven days of Inventory on hand throughout the year.
Accounts Receivable Turnover	Sales Accounts Receivable	Measures the rate at which Accounts Receivable are being collected on an annual basis. For example: an Accounts Receivable Turnover Ratio of 8.00 means that the average dollar volume of Accounts Recievalbe are collected eight times during the year.
Average Collection Period	360 A/RTurnover	Converts the Accounts Receivable Turnover ratio into the average number of days the company must wait for its Accounts Receivable to be paid. For example: an Accounts Receivable Turnover ratio of 45 means that it takes the company 45 days on average to collect its receivables.
Accounts Payable Turnover	Cost of Goods Sold Accounts Payable	Measures the rate at which Accounts Payable are being paid on an annual basis. For example: an Accounts Payable Turnover ratio of 12.04 means that the average dollar volume of Accounts Payable are paid about twelve times during the year.
Average Payment Period	360 Accounts Payable Turnover	Converts the Accounts Payable Turnover ratio into the average number of days that a company takes to pay its Accounts Payable. For example: an Accounts Payable Turnover ratio of 30 means that it takes the company 30 days on average to pay its bills.