SERVICE SHEET Sta	ition:
Local Date/Time: GMT Date/Time:	
Field Team:	
GPS Location of Site:	
Equipment	
DAS S/N:	
Clock S/N:	
Sensor S/N Sensor Type:	
Get DAS initial Status:	
DAS Status (Control ⇒ Status)	
Acq: Start On / Off	
Events: of	
Disk 1: of Disk 2: of	
Temp: *Power: Input B	kup chg:
Ch: DS:	
*If Power is Low, follow instructions at the end "IF POWER IS	BAD"; otherwise
continue.	
Clock Status (Control ⇒ Status ⇒GPS)	
Sec since LL: Phase Diff S	V's·
Service	
1. Stop Acquisition (Control ⇒Status ⇒Stop Acq)	
• • • • • • • • • • • • • • • • • • • •	
2. Get RT130 parameters from the DAS	
Work with Config ⇒From DAS ⇒Edit ⇒Verify experiment name: _	
Get Sensor Serial Number: ⇒Channels⇒Details⇒record se	nsor S/N above
3. Swap Disks (wait for disk writing to finish)	
Orig. Disk 1 S/N: Size: Orig. Disk 2 S/N:	
LABEL these DATA Disks - do not reuse them until data are downloa	ded and backed up
Swap Disk 1 S/N: Size: Swap Disk 2 S/N:	Size:
5. Clear RAM (Control ⇒RAM ⇒Clear)	
6. Reset System (Control ⇒Reset) Note: this initializes the GPS	
7. Format Flash Disk (Control ⇒Format Disk ⇒ Disk 1: Disk	, O.
·	
8. Check Mass Position Offsets (Control ⇒Aux. Control ⇒Aux Char	inei)
Mass position must be within +1.5V to −1.5V	
Ch 1: V	
Ch 2: V	
Ch 3: V	
9. Monitor/Tap Test (Control ⇒Monitor ⇒Stream 1)	
Ch 1: Ch 2: Ch 3:	
10. Check Clock Status (Control ⇒Status ⇒GPS)	
Sec since LL:*Note clock MUST lock before starting	na acquisition
Phase Diff us (should be a small number)	ig acquisition
SV's:	
3v 5	
11 Chart Association (Control - Ctatus - Ctart Ass)	
11. Start Acquisition: (Control ⇒Status ⇒Start Acq)	
Start time:	-
12. Verify RAM Increasing (Control ⇒Status ⇒Update)	
Yes / No	
13. Force RAM Dump (Control ⇒ RAM ⇒ Dump)	
- · ·	⇒ Status ⇒
Verify RAM decreases and disk 1 or disk 2 increases (Control	⇒ Status ⇒
- · · · · · · · · · · · · · · · · · · ·	⇒ Status ⇒

14. V	Write .CFG File to Disk (Control⇒Status⇒DAS LP/WP) Tap the WRITE button to write the .cfg file to the disk. Verify that the value of disk energy used increases (Control → Status)					
Verify that the value of disk space used increases (Control ⇒Status).						
15. DAS status (Control ⇒Status)						
Acq: Start On / Off - NOTE Acquisition MUST be ON to get data						
	Events:	_	RAM:	of		
	*Disk 1:	of	Disk 2:	of		
	Temp:		Power: Input	Bkup chg:		
	Ch:		DS:			
	Firmware Version_	(Contro	l⇒Satus⇒Versio	ns)		
16. Check Mass Position Offsets (Control ⇒Aux. Control ⇒Aux Channel)						
Mass position must be within +1.5V to -1.5V						
Ch 1:	·	V				
Ch 2:		V				
Ch 3:		V				

Station ____

Make sure all plugs and connections have been replaced.

IF POWER IS BAD

Date _____

POWER: Check Power ONLY IF the station has Power Problems

NOTE: The following tests should be performed with the solar panels in full sun. Check solar panel is clean.

- 1. Disconnect the solar panel.
- 2. Test output of the batteries (12.5 13 Volts DC

WARNING: DO NOT test the current of the battery)

- 3. Test the voltage out of the power box to the DAS from pin A+ to C-. (Same as battery voltage measured above).
- ! Make sure the polarity is correct
- 4. Test the solar panel output (18 Volts DC)
- 7. Connect the solar panels to power box
- 8. Test the voltage at the battery terminals (Greater than the battery voltage measured above).

Comments: