

Merchant Info

Merchant _____

Address _____

City, State, ZIP _____

Merchant ID _____

System Info

Merchant Contact
Name & Phone _____

Card Processor
Name & Phone _____

Dealer Contact
Name & Phone _____

POS Package _____

From the *NETePay* menu bar, select **Setup** and choose **Merchant Parameters**

Setup NETePay Parameters

Merchant Information

Merchant ID: 000000000000 Terminal ID: 000 Bank ID: 0000 Merchant Category: Retail/QSR

☐ Enable PrePaid (Port 9100)

EPay Information

☐ Use Client / Server Password ☐ Go To System Tray when Minimized ☒ Truncate Sensitive Data

☐ Do Not Connect To FifthThird on Startup

Transport

☒ IP Only ☐ IP with DIAL Backup ☐ DIAL Only

Dial Backup Information

Comm Port: 1 Dial Prefix: Fifth Third Authorization Phone Number: 18776804236

IP Connection Information

Connect Timeout to Fifth Third: 3 Seconds.

OK Cancel Read ME

Merchant Information (Provided by Fifth Third)

Merchant ID	12 Digits Numeric; the Merchant ID (MID) assigned by Fifth Third
Terminal ID	3 Digits Numeric; the Terminal ID (TID) number assigned by Fifth Third
Bank ID	4 Digits Numeric; the Bank ID (CID) number assigned by Fifth Third
Merchant Category ID	Select either Retail, MOTO, or eCommerce as assigned by Fifth Third
Enable PrePaid (Port 9100)	Enable NETePay to accept PrePaid (Gift) transactions requests from the POS

IP Connect Information

Connect Timeout to 5 th 3rd	Sets the time in seconds to attempt an IP connection for each transaction before switching to dial for processing (if enabled). Allowable values are 3 to 40 seconds.
--	---

ePay Information

Use Client/Server Password	If you will be Client/Server Password operation, click the Client/Server Password box and enter the password to be used by the server in the box below the checkbox. You must also configure DSIClientX and ePay Administrator for Client/Server password protection using the same password to use this function.
Go To System Tray When Minimized	The selection box Go To System Tray when Minimized is unchecked by default. If you want to have the NETePay icon appear in the System Tray rather than in the Toolbar when minimized, check this

Do Not Connect To Fifth Third on Startup	The selection box Do Not Connect to Fifth Third on Startup is unchecked by default. When this option is unchecked, NETePay will check that it can establish a connection to the Fifth Third host before starting. If this box is checked, NETePay will start without testing the connection to the Fifth Third host.
---	---

Transport Information

<u>Select One:</u> IP Only IP with Dial Backup Dial Only	<ul style="list-style-type: none"> • IP Only – Select this option if you want NETePay to use only the Internet to process transaction with the Fifth Third Host. • IP with Dial Backup – Select this option if you want to use the Internet as the primary means of communication with Fifth Third and to have automatic direct dial backup operation occur when Internet service is interrupted. This option requires that you install a Datacap DialLink modem on an available COM port. <i>NETePay only operates with a Datacap DialLink modem for backup operations – third party modems are not supported.</i> • Dial Only – Select this option if you want to use the Datacap DialLink modem and phone line as the primary means of communication with Fifth Third. This option requires that you install a Datacap DialLink modem on an available COM port. <i>NETePay only operates with a Datacap DialLink modem for dialup operations – third party modems are not supported.</i>
---	---

Dial Backup Information

Comm Port	<ul style="list-style-type: none"> • Comm Port – Select the COM port number where the Datacap DialLink modem is attached. Make sure not to use a port number used by another device. Allowable ports are 1-255.
Dial Prefix	<ul style="list-style-type: none"> • Dial Prefix – If the phone system being used with the Datacap DialLink modem requires dialing a prefix to get an outside or long distance line, enter it here. A 'W' (wait for dial tone) or a ',' (comma – wait 2 seconds before dialing next digit) are the most common along with 8 or 9. For example "8,"
Fifth Third Authorization Phone Number	<ul style="list-style-type: none"> • Fifth Third Authorization Phone Number – This number will automatically be filled in for the recommended access number to Fifth Third. You may change this number if you are having problems reliably communicating with the host. Contact your merchant service provider or Fifth Third directly to obtain alternate access phone number(s).

Refer to the **NETePay Guide for Fifth Third Host** (on the NETePay CD in PDF format) for complete information on setup and configuration.

Datacap Systems reserves the right to make product changes and improvements without notice or obligation to notify any persons or entity of such changes or improvements. Datacap is not responsible for typographical errors or inaccuracies due to inability to read or interpret customer supplied information. DataTran network software modules for DataTran are provided 'as is'. Datacap Systems makes no warranty of any kind with regard to this software, including but not limited to, the implied warranties of merchantability and fitness for a particular purpose. Datacap Systems shall not be liable for any errors or for incidental or consequential damages in connection with the use of the software or other programmed information, including customer supplied information.